



Archive contents

	<p>certification</p> 
1st level files and folders	2nd level files and folders

- The file you are reading : **readme.pdf** and the Usage General Conditions that have been added in **cgu_deltat_v4.pdf**
- The folder **certification** contains the certification book (**DGDDI - CertifEdiDeltaT - Opérateur.pdf**) and the dataset (xml files and a summary statement) in the archive **certif_deltat_jeux_donnees.zip** .
- The folder **outils** contains the frequently asked questions (**DGDDI - FAQ - Opérateur.pdf**), the Mareva wrappers and 2 examples for declaration ie015. , details for Docement d'Accompagnement format (**format_docaccpt.pdf**), the file **mapping_balises_xml_v20.00.pdf** shows the mapping between long and short names for XML tags. French tags are not included. The file **messages_erreur_generiques.pdf** contains the error code list in case of functional reject, the file **mapping_noms_courts_balises_xml.pdf** maps the short name that appears in the functional

error with the data group, the files `ref_code.csv` and `ref_libelle.csv` contain the codes and labels for the code list elements.

Reminder : The Mareva file **enveloppes_mareva.pdf** contains some help to write the wrapping part necessary to send any message to DeltaT. This wrapper encompasses 2 parts : one for connection and one for message. A prerequisite is that a PEDI relation in the Formation environment for ROSA (during test period) , or production environment (for Production) will have to exist containing the connection provider SIRET, the application name (Delta-Tform), the agreement reference number (provided by Customs). The public part of the certificate will have to be supplied to Customs. If that PEDI relation already exists, Customs will add the new application Delta-Tform. The email address to use to send messages for traders is deltatform@edi.douane.finances.gouv.fr
The outils folder also contains the archive `annexe_docs_ie044.zip` that has examples and an explanation about how to encode the IE044 message for unloading remarks.

- The folder **referentiels** contains the file **liste_msgs_comp_nsti_deltat.ods** . That applies to the messages for traders present in NSTI and/or DeltaT for emission/reception. So you will see the new messages created in DeltaT or those in NSTI that changed their name. There are 27 messages, from which 7 are to be sent by traders. The dictionnary for the 27 messages with rules and conditions is in the file

DELTA-T_CDS_Opérateur_Dictionnaire_des_messages_v2.1.ods .

The file `DELTA-T_CDS_Opérateur_Document_principal_v2.0.docx` is the Service Contract for Traders, the file `DELTA-T_CDS_Opérateur_Tables_Referentiels_v2.0.ods` contains the code lists useful for Transit (one tab per list). Finally **modeles_messages_operateur.zip** contains all the XML templates for the 27 messages using an easily readable form :

Ex: `<ArrRejDatHEA142>R, n8</ArrRejDatHEA142>`

`ArrRejDatHEA142` is the tag name (tag name is formed from the first three letters of each tag word)

`R, n8` means required, numeric format 8 characters.

You can also find : `O` for optional, `D` for dependant. `n..12` means till 12 characters whereas the archive **schemas_messages_operateurs.zip** encompasses all the XSD schemas for the 27 messages, split into "emission", "reception" and "references" for the basic schemas.